




EZ-Scan® Install Preparations.

Ver: 1.0

Because of the add security layers now used in Windows 7/8/10 you should use the following step to insure that all directories will have the proper security rights and the driver for the check scanners will install all the needed files to work correctly.

1. Must login with a user that has **LOCAL** admin rights to install files.
2. Windows's "User Account Control Settings" must be minimized to install drivers. If you have to change you must reboot for change to take effect. You can change after installing ALL the software but the user will not be able to make changes in EZ-Scan®. Turning on will not let the operator to make changes in the registry which is where we keep most of our settings.



3. You **MUST** load the appropriate check scanner driver from the list below. Do **NOT** use the CD that came with the scanner. It will be outdated and does not include the required software (API) needed for our software to work.

Digital Check Teller Scan products – http://pstinc.net/pub/DCC%20TellerScanDriver_V12.77.exe

Panini Vision X - <http://pstinc.net/pub/Pamini%204.0.2%20Universal%20Installer%20-%20Client.zip>

Canon CR-25/55 - <http://pstinc.net/pub/Canon%2025-55%20SU%20V1040%20Driver.exe>

Canon CR-50-80 - <http://pstinc.net/pub/Canon%2050-80%20SU%20V11-V17%20Driver.exe>

When you install the scanner driver, the scanner **MUST BE UNPLUGGED**. Also right click and “Run as administrator” should be used. (Note: These drivers should not interfere with any existing check scanning drivers)

4. After installing the check scanner driver, please plug in the check scanner a let Winnows load the proper drivers. (This could take up to 3 minutes in some cases, you can check in Device Manager to make sure the scanner installed properly. You should not see any “Unknown Devices.”)
5. You are now ready to install your EZ-Scan® software. Just right click the EZ-Scan® install file and “Run as administrator” and all files should load properly.
6. This is an optional step but recommended in most cases. Once you see the EZ-Scan® icon on the desk top. Right click and choose “Properties” then “Compatibility” and check the “Run this program as an administrator” (Below screen may vary based on OS).

